

First Time Setup Wizard

Basic Cumulus and Station Setup

| | | | | | |
|---|--------------------------------------|----------------------------------|-------------------------------------|--|---|
| Location Geographic Information | Units Temperature Wind etc | Station Setup your PWS | Logging Logging intervals | Internet Configure web hosting | Actions Enable interval actions |
|---|--------------------------------------|----------------------------------|-------------------------------------|--|---|

| | |
|----------------------------------|---|
| Name | <input type="text" value="Querol-Bonany-Cal Pau"/> |
| | <small>ⓘ A short name for your weather station. This will be used in headings and reports etc</small> |
| Description | <input type="text" value="L'Alt Camp Catalunya"/> |
| | <small>ⓘ A longer description of your weather station. This will be used to add additional information to the web pages</small> |
| Latitude (required) | <input type="text" value="41.393554"/> |
| | <small>ⓘ Enter your latitude as a decimal degrees value (+ve = North, -ve = South).</small> |
| Longitude (required) | <input type="text" value="1.466573"/> |
| | <small>ⓘ Enter your longitude as a decimal degrees value (+ve = East, -ve = West).</small> |
| Altitude (required) | <input type="text" value="609"/> |
| | <small>ⓘ Enter the elevation of your weather station above sea level. This is used for pressure calculations so get it as accurate as you can</small> |
| Altitude units (required) | <input type="radio"/> feet <input checked="" type="radio"/> metres |

First Time Setup Wizard

Basic Cumulus and Station Setup

| | | | | | |
|---|--------------------------------------|----------------------------------|-------------------------------------|--|---|
| Location Geographic Information | Units Temperature Wind etc | Station Setup your PWS | Logging Logging intervals | Internet Configure web hosting | Actions Enable interval actions |
|---|--------------------------------------|----------------------------------|-------------------------------------|--|---|

| | |
|-------------------------------|---|
| Temperature (required) | <input type="text" value="Celsius"/> |
| Wind (required) | <input type="text" value="Kilometres per hour (km/h)"/> |
| Pressure (required) | <input type="text" value="Hectopascal (hPa)"/> |
| Rain (required) | <input type="text" value="Millimetres"/> |

ⓘ Think carefully, you cannot change these later and retain any existing data

Previous

Next

First Time Setup Wizard

Basic Cumulus and Station Setup

Location
Geographic Information

Units
Temperature Wind etc

Station
Setup your PWS

Logging
Logging intervals

Internet
Configure web hosting

Actions
Enable interval actions

Log interval (required) 10 minutes
Frequency of Cumulus log entries - set your station to the same

Log Rollover

Rollover Time (required) 9am midnight

Previous Next

First Time Setup Wizard

Basic Cumulus and Station Setup

Location
Geographic Information

Units
Temperature Wind etc

Station
Setup your PWS

Logging
Logging intervals

Internet
Configure web hosting

Actions
Enable interval actions

Station type (required) Ecowitt Cloud

Station model FROGGIT HP1000SE PRO
A descriptive name for your station type, this will default to the station type if blank. You can change this to whatever you like

▼ **Ecowitt Cloud Access API**

Application Key: 49FF631705298BA7EDE7D5F7913369F9
Enter the Application Key you have created in your user profile on the ecowitt.net web site

API Key: dc0c0591-e1da-4085-8670-d0ba5de99fa6
Enter the API Key you have created in your user profile on the ecowitt.net web site

Station MAC/IMEI address C4:5B:BE:6D:70:EF
Enter the MAC/IMEI address of your station/gateway.
MAC format is XX:XX:XX:XX:XX:XX
IMEI format is 15 or 16 digits
You can find this on your device in the Ecovitt WS View or WS View Plus app

First Time Setup Wizard

Basic Cumulus and Station Setup

Location Geographic Information **Units** Temperature Wind etc **Station** Setup your PWS **Logging** Logging intervals **Internet** Configure web hosting **Actions** Enable interval actions

Web Hosting Site

Local Copy

Enable local file copy of standard files

- Rather than using uploads, simply copy the standard web files to another folder.*
- Typically this would be used when 'self hosting', when FTP would not be appropriate/efficient.*
- It can be used in conjunction with uploading.*

Upload

Enable upload connections

- Enable web site uploads via FTP, FTPS, SFTP, or PHP*

[Previous](#) [Next](#)

First Time Setup Wizard

Basic Cumulus and Station Setup

Location Geographic Information **Units** Temperature Wind etc **Station** Setup your PWS **Logging** Logging intervals **Internet** Configure web hosting **Actions** Enable interval actions

Normal Interval Configuration

Interval Settings

Enable Enable normal update interval

- Enable the update interval timer so normal interval actions can take place*

Normal interval

- Interval between normal updates in minutes*

Real time Settings

Enable Enable real time update interval

- Start the real time timer so that any real time actions can take place*

[Previous](#) [All Done!](#)